IJCAD

Single license Setup manual



IJCAD

Single license setup manual

table of contents

01 Before installation

01-01 Procedure for introducing IJCAD ····· 004
01-02 Recommended operating environment ····· 004
01-03 Precautions ····· 005

02 Create an IJ account

02-01 IJ account registration/login ····· 006

03 How to operate licenses

03-01 Creation of license team ····· 008
03-02 Belong to the licensing team ····· 011
03-03-01 License assignment ····· 012
03-03-02 Cancellation of license assignment ····· 016

04 Installing IJCAD

04-01 Downloading IJCAD ····· 017
04-02 Installing IJCAD ····· 019

05 Starting IJCAD

05-01 Login and activation ····· 023

06 How to use in an offline environment

06-01 About license rental ····· 026
06-02 Logout of IJ account (account deactivation) ····· 027
06-03 License lending and approval ····· 028
06-04 Offline license activation ····· 031
06-05 Manual return of license ····· 032

07 Update Installation

07-01 Before Update Installation ····· 035
07-01 Update Installation procedure ····· 035

08 Uninstalling IJCAD

08-01 Uninstalling IJCAD ····· 037

09 My Account

09-01 Change account information ····· 040
09-02 Addition of login method ····· 041


＊＊＊

Revision History

February 02, 2026 First edition of single license setup manual issued
March 02, 2026 Second edition of single license setup manual issued
April 01, 2026 Third edition of single license setup manual issued
June 01, 2026 Fourth edition of single license setup manual issued
July 01, 2026 Fifth edition of single license setup manual issued
August , 2026 Sixth edition of single license setup manual issued

01 Before installation

01-01 Procedure for introducing IJCAD



01-02 Recommended operating environment

The following operating environment is necessary for this product.
Please note that the operating environment is subject to change without notice.
Please check the IJCAD help center
(https://support.ijcad.jp/hc/ja) for the latest information.

CPU	Minimum Core i 5 More than Core i 7 (recommended)
RAM	Minimum 8GB More than 16GB (recommended)
HDD(SSD)	PF:More than 1.82GB Civil:More than 1.37GB Mechanical:More than 2.01GB Electrical:More than 1.91GB

	Arch/ Arch+:More than 2.20GB
PC/OS	Windows 11 (24H2) (25H2)
Display card	2GB GPU (recommended)
OPTION	.NET 8(※)
	[Only when using VBA] Microsoft Visual C++ 2010 Redistributable Package(※)

※ About .NET 8
If .NET 8 is not installed on your PC,
it will be installed along with the installation of IJCAD 2026.

※ About Microsoft Visual C++ 2010 Redistributable Package
If "Microsoft Visual C++ 2010 x64 Redistributable" is not installed on your computer, please install it by yourself from the Microsoft website.

01-03 Precautions

■ During installation, an application called "B-rite Runtime 3" will also be installed.
B-rite Runtime 3 is an application required to run the product, so please do not delete it.



■ The icon is different for each product

▼PF ▼Civil ▼Mechanical/Mechanical+ ▼Electrical ▼Arch/Arch+








02 Create an IJ account

02-01 IJ account registration/login


If you already have an account on one of the sites below, you do not need to register for a new IJ account. You can log in to your IJ account using your existing account.

- IJCAD.jp（https://www.ijcad.jp/）
- CAD data conversion service [DARE]（https://www.caddare.com/）


1. Access IJStore
   Access IJStore (https://manage.ijcad.jp/) to register and log in to your IJ account.




2. New registration
   Enter your email address and password, and click the [新規登録] button.



3. Confirm registered email address
   An email titled「【IJCAD】仮登録完了のお知らせ」will be sent to the registered address.
   Please click the link in the email.



4. Registration
   The registration is complete when「ユーザーの本登録を完了しました」pop-up appears.



   When you click the［ログイン］button, the screen will change.
   enter the email address and password you registered.。

5. IJStore(https://manage.ijcad.jp/)will be available.

03 How to operate licenses

With a single license, an administrator can assign a license to a member and allowing the assigned person to use the license.

- **When operating a license by an individual**
  There is no need to invite members, so please proceed to ”03-03 License assignment ”.

- **When operating multiple licenses on a company/group（License administrator）**
  The member to whom the license will be assigned must be invited to the license team.
  Please proceed from ”03-01 Creating of license team”.


- **When operating multiple licenses on a company/group（license user）**
  Please only perform ”03-02 Belonging to the license team”.

03-01 ライセンス利用チームの作成


Creating a licensing team

＊Only email addresses that have completed account registration with IJStore can receive invitations. Before inviting, please make sure that the email address of the member you want to invite is already registered.

1. Invite members
   「ライセンスの管理」>「メンバー管理」>click[メンバー招待] button.



2. Completion of invitation
   Enter the email address of the member you want to invite and click the [送信する] button.



Once the invited user accepts, membership in the team will be completed.



◆ Bulk invitation
   By loading CSV, you can invite members in bulk.

1. Get template
   [ー Click the [一括招待] button.



When you click [テンプレートを取得] on the「メンバーの一括招待」screen, a CSV file will be downloaded.



2. Fill in CSV file
   Open the CSV file downloaded in step “1. Get template” and fill in the information below.
   ・email address
   ・username
   ・Administrator settings
   Entry example：

	A	B	C
1	user1@example.com	山田 太郎	1
2	user2@example.com	鈴木 一郎	0
3			
4			

   ＊In the administrator settings, enter 1 if you want to invite as an administrator, and 0 if you want to invite as a user.

3. Load CSV file
   Follow the steps in “1. Get template” to open the「メンバーの一括招待」screen.
   Click the [ファイルを選択] button and select the CSV file you saved in ”2. Fill in the CSV file”.




Bulk invitation has been completed.




03-02 Belong to the licensing team

If you want to use a license owned by a company or group, you must belong to that license team.

1. Approve the invitation to the licensing team
   An internal buyer or management company will invite you to join the team.
1. If you receive an email saying "【IJCAD】〇〇 様よりライセンスチームに招待されました," please click the link in the email.



2. Completion of approval
   On the「チームの承認」page, click the [承認する] button.



This completes your membership in the license team you were invited to and allows you to use the licenses held by the team.


＊You cannot belong to another license team while renting your license.
Please be sure to return your license before accepting the invitation.
Please check the [Multi-license Operation Manual] for details on the lending function.

03-03-01 License assignment

Licenses are allocated on a per-license basis.

◆ How to assign licenses individually

1. License assignment
   Click [ライセンスの管理] > [シングルライセンスの管理].




The licenses you own will be displayed, so click [割り当て].



2. Deciding who to assign
   Select the users to whom you want to assign licenses from the checkboxes and click the[決定] button.



The assigned users are listed in the red frame below.



◆ How to assign licenses in bulk

1. Get template
   [ー Click the [CSV 一括割り当て] button.



When you click [テンプレートを取得] on the「CSV 一括割り当て」screen, a CSV file will be downloaded




2. Fill in CSV file
Open the CSV file downloaded in step “1. Get template” and fill in the information below.
・email address
Entry example：

	A	B	C	D	E	F
1	製品名	ライセンス区分	ユーザー名	有効期限	シリアルキー	メールアドレス
2	IJCAD STD	ソフトウェア・サブスクリプション				user1@example.com
3	IJCAD PRO	ソフトウェア・サブスクリプション				user2@example.com
4	IJCAD Mechanical	ソフトウェア・サブスクリプション				user3@example.com
5						


3. Load CSV file
Follow the steps in “1. Get template” to open the「メンバーの一括招待」screen.
Click the [ファイルを選択] button and select the CSV file you saved in ”2. Fill in the CSV file”.



A confirmation screen will appear. Click [Assign].



Once the results are displayed, click [Close] to complete the bulk assignment.



※ Licenses will not be assigned in the following cases:

- Users who already have a single license assigned
- Attempting to assign another user to an already assigned license
- Email addresses that do not exist within the license team
- Duplicate email addresses in the CSV (subsequent entries from the second onward will not be assigned)

03-03-02 Cancellation of license assignment

License assignments can be canceled one by one or all at once.

◆ Cancel one by one

1. Select users to cancel
   Click on the user you want to cancel.
   [ライセンスとユーザーの割り当てを解除します。よろしいですか？] pop-up will appear, click [OK].



   The clicked user will be canceled from the group.

◆ Cancel allocation in bulk

1. Selection of batch cancellation
   Click the [一括解除] button
   [アタッチされているユーザーを一括解除します。よろしいですか？] pop-up will appear, click [OK].




   All assigned users will be canceled in bulk.

04 Installing IJCAD

04-01 Downloading IJCAD

◆ Download from downloadable software page

1. Log in to IJStore（https://manage.ijcad.jp）
   Log in with your registered email address and password.
2. Open the downloadable software page.
   Click [ライセンスの利用] > [ダウンロード可能ソフト] in the side menu.



3. Download the installer
   Click the icon in the download column to download the product installer.



*Licenses will not be displayed unless you are a member of the license team.
*If there is multiple software available for download and you are not sure which one to download, please contact your company's administrator.

◆ Download from Product Downloads page

1. Log in to IJStore（https://manage.ijcad.jp）
   Log in with your registered email address and password.
2. Open the product download page
   Click [ライセンス管理] > [製品ダウンロード] in the side menu.




3. Download the installer
   Click[ダウンロード] to download the product installer.




04-02 Installing IJCAD


1. Decompress the installer (unzip)
   Right-click the downloaded IJCAD installer and click［すべて展開］.
   The installer is a compressed file. Please be sure to decompress it.




2. Select decompression destination
   The「展開先の選択とファイルの展開」dialog is displayed.
   There is no need to change the deployment destination. Just click the［展開］button.



   Once the decompression is complete, a folder will be created based on the installer name.




3. Execute [setup.exe]
   Open the decompress file and right click［setup.exe］. Find and click［管理者として実行］.



「ユーザーアカウント制御」dialog may appear. Click「はい」to start the installer.


4. Launch the installer
   When the installer starts, click [Next].



5. Confirm the license agreement
   Please read the IJCAD Software License Agreement, Maintenance Service Terms, and Support Policy (links).
   If you agree, check the two checkboxes and click [Next].




6. Select installation destination
   Just click the [Install] button.
   You can also select the installation destination folder from [･･･].



7. Installation
   Installation will begin.



8. Installation completed
   Click [Finish] to exit, and click [Launch] to start IJCAD.



Once the installation is complete, an IJCAD icon will be added to the desktop or start menu.



∗ At the same time, ”B-rite Runtime 3”, an application to authenticate the IJCAD license, will be added.
This application is required for license authentication, so please do not delete it.



05 Starting IJCAD


05-01 Login and activation

1. Starting IJCAD for the first time
   Double-click the IJCAD icon on the desktop to start IJCAD.



While the software is primarily intended to be used by the same user who installed it, please refer to the following article if you must use it with a different account.
インストールユーザーと異なるユーザーで利用する場合の注意点

2. Preparation for login
   When you start IJCAD, an authentication screen will be displayed first.
   Click the［Login］button to display the login screen.




＊By checking ”☑ Use a browser”,
you will log in via the browser you normally use.

3. Log in to your IJ account
   You need to log in to your IJ account.
   After entering the registered email address and password, click the［Login］button.



When license authentication is completed using the logged-in account, IJCAD will start.

4. Set file associations
   When you start it for the first time, the following setting screen for association with DWG will be displayed. Select as required.
   If you select「Always reassociate DWG with IJCAD(Recommended)」in the first line, DWG will always be associated with IJCAD.
   From now on, double-clicking the DWG file will open IJCAD.



5. Start IJCAD
   IJCAD startup has completed.

06 How to use in an offline environment

By using the license lending function, you can use IJCAD even in an offline Environment.

06-01 About license rental


With the new license method, IJCAD can be used even in an offline environment by authenticating the license using the license lending function.

The new license method IJCAD normally performs license authentication online through the network. Therefore, it cannot be used in an offline environment without the lending function. If you want to use it offline, be sure to authenticate the license from ”Rent a license”.

◆ **Use IJCAD offline**



（＊1）▼ Authentication screen displayed in IJCAD with new license method [B-rite]



06-02 Logout of IJ account (account deactivation)


If the drawing screen is displayed when you start IJCAD, online license authentication is being performed through the logged in IJ account.
In this state, you cannot use it offline, so log out of your account.

1. Start B-rite Runtime
   Start B-rite Runtime3, which manages IJCAD authentication information.




◂ B-rite Runtime 3 icon


2. Log out
   The B-rite Runtime console displays the users currently logged in to IJCAD.
   Right-click the displayed username and click [Logout].



3. Log out from all applications
   Next, the message「All authorized applications will be logged out.Lending licenses will be returned automatically when you are online.Do you want to log out?」will be displayed. Click the [OK] button.



4. Logout completed
   Logout is complete when the username and license disappear from the B-rite Runtime console.




06-03 License lending and approval


If an authentication screen is displayed when you start IJCAD, you can rent a license.

◆Creating a rental file


1. Create a rental file (●●. seed)
   Start IJCAD and open the B-rite license authentication screen.
   Click the [Lending] button in the ”Authenticate offline” column.



2. Enter IJ account information
   Enter the email address, password, company name, and username to identify the lender, then click [Save the file].
   ∗Please note that the lending function does not support Google login or Microsoft login, so if you wish to use the lending function, please refer to add email authentication in [08-02 Addition of login method] for email authentication. Please add.



3. Selection of rental period
   Select the end date of the rental period and click the [OK] button.



4. Save the rental file (●●. seed) in any location
   An explorer will appear where you can save the rental file (●●. seed).
   Save itsomewhere easy to find, such as your desktop.
5. Completion of creation of rental file
   If the ●●.seed file has been created, the rental file has been created correctly.


◆Issuance of authorization file

Issue the authorization file with IJStore. This process requires working in an online environment.

Please prepare the rental file (●●. seed) you created.

If the rental file was created on a different machine, use a USB or other device to move it to the online machine.

1. Log in to IJStore
   Log in to IJStore (https://manage.ijcad.jp/).
   You must log in to the account that issued the license.
2. Open the rental file upload page
   Upload the rental file and authenticate the license.
   Click [ライセンスの管理] > [ライセンスの貸し出し] in the side menu.



3. Upload the rental file
   Drag and drop the rental file (●●. seed) onto the license rental page.
   Alternatively, click [ファイルを選択], select the rental file (●●. seed) from Explorer, and click the [開く] button.




4. Save the authorization file
   When you select a rental file, it will be automatically uploaded to the server and the license will be authenticated.
   If the authentication passes, the authorization file (●●.au1) will be automatically downloaded.
   Confirm that the authorization file (●●.au1) has been downloaded to the specifiedfolder, such as the download folder.

* Once the authorization file is issued, only one license you own will be in use. Please note that the license you are using cannot be used on other machines until the license is returned.


06-04 Offline license activation

Import the authorization file (●●.au1) saved in [06-03 ◆Issuing authorization file] into IJCAD and perform offline license authentication. This process can be done offline.
If the authorization file was issued on a different machine, use a USB etc. to move it to the machine where you issued the rental file (●●. seed).。

1. Import authorization file
   Start IJCAD, open the authentication screen, and click the [Import] button in the ” Authorization file ” field.



2. Select authorization file
   Explorer opens for importing the authorization file. Select the authorization file (●●.au1).
3. Launch offline
   If the authorization file is successfully imported, a confirmation dialog will be displayed. Click the [OK] button to start the application.



After that, you can start it offline until the expiration date set at the time of lending or the license expiration date, whichever comes first.

06-05 Manual return of license

If you want to return the license earlier than the date specified when renting the license, you can also return it manually.

◆Create return file (●●.au2)

1. Start B-rite Runtime

   Start B-rite Runtime3, which manages IJCAD authentication information.




◂ B-rite Runtime 3 icon

2. Return of license ①


   The B-rite Runtime console displays the users who are currently lending IJCAD licenses and the name of the application being rental.

   Right-click the application name and click [Return of license].




3. Return of license ②

   When the message appears, Click the [OK] button.



*The license return process will be completed if done online.
The following steps should only be performed by those who will be returning licenses in an offline environment.


4. Save the returned file
   A return file (●●.au2) will be created to return the license.
   Save it somewhere easy to find, such as your desktop.
5. Saving of returned file completed
   When the message "Exported authentication file" appears, click the [OK] button.
   Saving of the return file is now complete.



◆Return of license

Return the license at IJStore. This process requires working in an online environment.
Please prepare the return file you created (●●.au2).
If the return file was created on a different machine, use a USB or other device to move it to the online machine.

1. Log in to IJStore
   Log in to IJStore(https://manage.ijcad.jp/).
   You need to log in to the account to which you lent the license.
2. Open the license rental page
   Click [ライセンスの管理] > [ライセンスの貸し出し] in the side menu.



3. Open the upload tab for returned files
   On the License Borrowing page, you will see the Borrowing and Returning tabs.
   To return the license this time, click on the [返却] tab to open it.



4. Upload the return file
   Drag and drop the return file (●●.au2) into the return tab.
   Alternatively, click [ファイルを選択], select the returned file (●●.au2)
   from Explorer, and click the [Open] button.



5. Completion of return
   If the license has been successfully returned, the message [処理が完了しました]
   will be displayed. This completes the return of rental license.



Once the license return is completed, the license that was in use will be released.
It can be used both online and offline.

07 Update Installation

When you want to update version of the installed product, update installation is necessary.

※Update installation is not required when installing IJCAD 2025 SP0.

Update installation differs from version up and means to update within the same fiscal year version.

Example:

Update installation: IJCAD 2026 SP0 → IJCAD 2026 SP1

Version up: IJCAD 2025 SP1 → IJCAD 2026 SP0

07-01 Before Update Installation


Although the information of CUI and template customization could be inherited without transit operation, first take your backup before update installation for your safety.

- Cuix file, etc.
  ⇒C:¥Users¥(User Name)¥AppData¥Roaming¥IntelliJapan ¥IJCAD(Grade)¥R26¥en-US¥Support

- Template File
  ⇒C:¥Users¥(User Name)¥AppData¥Local¥IntelliJapan ¥IJCAD(Grade)¥R26¥en-US¥Template

07-02 Update Installation procedure


1. Download the latest Installer
   The latest version can be downloaded from the WEB page (https://manage.ijcad.jp/trials/downloads)
2. Launch the Installer
   Please Unzip the downloaded folder, right-click on [setup.exe] in the folder, and run it as an administrator. The installer will start.



3. Update Installation

   After launching the installer, a dialog like the right picture appears.

   Click [はい] button



4. Installation

   The installation will begin, so please wait until it is complete.

   The update installation is now complete.

*If the update installation does not go well, please uninstall IJCAD once and then perform a new installation.

08 Uninstalling IJCAD

08-01 Uninstalling IJCAD


Uninstallation is possible in two ways from [アプリと機能] and from [コントロールパネル].

◆Uninstall procedure from [アプリと機能]


1. Go to the uninstallation screen
   Right-click the Windows Start menu,
   click [Settings] > [Apps] > [Installed Apps],
   then follow the steps below to open the uninstall menu.



2. Uninstall
   The installer will start, and a confirmation message will be displayed, so click the [はい] button.



3. Completion of uninstallation
   When the completion dialog appears, click the [Finish] button.




4. Delete user data
   After uninstalling, please delete your user data.
   C:¥Users¥[username]¥AppData¥Roaming¥IntelliJapan
   ¥IJCAD [product name or grade] ¥R25

◆Uninstall procedure from [コントロールパネル]


1. Go to the uninstallation screen
   Open Control Panel and select [プログラムのアンインストール].



2. Uninstall
   Select the IJCAD you want to uninstall from the list, right-click the mouse, and click [アンインストール] from the menu.



   The installer will start, and a confirmation message will be displayed, so click the [はい] button.



3. Completion of uninstallation
   When the completion dialog appears, click the [Finish] button.



4. Delete user data
   After uninstalling, please delete your user data.
   C:¥Users¥ [username]¥AppData¥Roaming¥IntelliJapan
   ¥IJCAD [product name or grade]¥R26

＊If you do not use IJCAD, please uninstall B-rite Runtime 3 at the same time.
The procedure is the same as uninstalling IJCAD, and you can uninstall from [アプリと機能] and [コントロールパネル].
There is no need to delete user data.

09 My Account

09-01 Change account information


You can change the following account information from the My Account page.

◆Change username
◆Add/remove authentication provider
◆Change/add password
◆Delete an account

Click the icon in the header menu at the top right of the page to display your [マイアカウント].



You can edit each item by clicking the icon in the edit column.
*Email address cannot be changed.
If you would like to change your email address, please contact support.



◆Authentication provider
The authentication provider can cancel ”Google authentication”, ”Microsoft authentication”, and ”email authentication” for logging into IJStore.

◆ Password
You can change your password.
Also, if you want to add email authentication, you can add email authentication by entering your password.

◆ Username
You can change your username.

09-02 Addition of login method

It is possible to add email authentication, Google authentication, and Microsoft authentication.

◆ Add email authentication


1. Open My Account
Open [マイアカウント] by clicking the icon in the header menu at the top right of the page.



2. Edit password
Click the edit icon in the password field.



3. password setting
The password setting screen will be displayed. Enter your new password and click the「送信」button.




Email authentication has been added to the authentication provider of My Account.

◆ Addition of Google login and Microsoft login

1. Select login method

   Open your IJ account login page and click the ”Google” or ”Microsoft” button.



2. Addition of authentication method

   Select or log in to the Google account with the same email address as the IJ account to which you want to add Google authentication or Microsoft authentication.

   If you check your My Account, it will be added to your authentication provider list.

項目	値	編集
認証プロバイダー	Google 認証、メール認証	
メールアドレス	[redacted]@gmail.com	
パスワード	••••••••	
ユーザー名	[redacted]	