

IJCAD

USB license Setup manual





USB license setup manual

table of contents

01

Before installation

- 01-01 Procedure for introducing IJCAD..... 004
- 01-02 Recommended operating environment 004
- 01-03 Precautions 005

02

Installing IJCAD

- 02-01 Downloading IJCAD..... 006
- 02-02 Installing IJCAD 008

03

USB update

- 03-01 Downloading USB Updater 012
- 03-02 Updating an empty USB 013
- 03-03 Update configured USB 014

04

Starting IJCAD

- 04-01 Starting IJCAD for the first time..... 016

05

Update Installation

05-01 Before Update Installation 018
 05-01 Update Installation procedure 018

06

Uninstalling IJCAD


06-01 Uninstalling IJCAD 020

Revision History

February 2, 2026 First edition of USB license setup manual issued
 March 02, 2026 Second edition of USB license setup manual issued
 April 01, 2026 Third edition of USB license setup manual issued
 June 01, 2026 Fourth edition of USB license setup manual issued

01 Before installation

01-01 Procedure for introducing IJCAD



01-02 Recommended operating environment

The following operating environment is necessary for this product.

Please note that the operating environment is subject to change without notice.

Please check the IJCAD help center

(<https://support.ijcad.jp/hc/ja>) for the latest information.

CPU	Minimum Core i 5 More than Core i 7 (recommended)
RAM	Minimum 8GB More than 16GB (recommended)
HDD(SSD)	PF:More than 1.82GB Civil:More than 1.37GB Mechanical:More than 2.01GB Electrical:More than 1.91GB Arch/ Arch+:More than 1.0GB
PC/OS	Windows 11 (24H2)

Display card	2GB GPU (recommended)
OPTION	.NET 8(※)
	[Download IJCAD from DVD] DVD-ROM Drive
	[Only when using VBA](※) Microsoft Visual C++ 2010 Redistributable Package(※)

- ※ About .NET 8
If .NET 8 is not installed on your PC,
it will be installed along with the installation of IJCAD 2026.
- ※ About Microsoft Visual C++ 2010 Redistributable Package
If "Microsoft Visual C++ 2010 x64 Redistributable" is not installed on your
computer, please install it by yourself from the Microsoft website.

01-03 Precautions

■ The new USB license requires you to enter a valid period using USBUpdater. However, updating the USB may not be possible in proxy server environments or highly secure environments.

Therefore, please be sure to perform a connection test beforehand.

Reference: [New USB] About the USBUpdater Connection Test

<https://support.ijcad.jp/hc/en/articles/34187939763865>

■ The icon is different for each product

▼PF



▼Civil



▼Mechanical/Mechanical+



▼Electrical



▼Arch/Arch+



- When updating the USB, do not disconnect the USB during the update.
- Please do not update by inserting two USBs.

02 Installing IJCAD

02-01 Downloading IJCAD

◆ Download from Product Downloads page

1. Access download page

You can download the installer from the web page below.

<https://manage.ijcad.jp/trials/downloads/no-auth>

Click[ダウンロード] to download the product installer.

The screenshot shows a web interface for downloading IJCAD software. At the top, there are two buttons: "グレードの選び方" (Select Grade) and "インストール方法はこちら" (Installation Method is Here). Below these are nine product cards arranged in a 3x3 grid. Each card displays the product name, version, and architecture (64bit), along with a yellow "ダウンロード" (Download) button. The first card, "汎用 CAD IJCAD: LT [64bit]", has its download button highlighted with a red rectangle. The other cards are: "汎用 CAD IJCAD: STD [64bit]", "汎用 CAD IJCAD: PRO [64bit]", "機械設計用 CAD IJCAD: Mechanical [64bit]", "機械設計用 CAD IJCAD: Mechanical+ [64bit]", "建設・土木用 CAD IJCAD: Civil [64bit]", "電気設計用 CAD IJCAD: Electrical LT [64bit]", "建築用 CAD IJCAD: Arch [64bit]", and "建築用 CAD IJCAD: Arch+ [64bit]".

◆ Download from DVD

* Only applicable to customers who purchased the installation DVD.

1. Insert the DVD into your computer's disc drive.


It varies depending on the computer environment as follows.

Click [LoadMenu.exe の実行].




2. Open the setup screen

Click on the icon of the product you want to download.



3. Launch the installer

Click the icon for the grade of product you want to install.



The installer will start.


Proceed to "2-2 Installing IJCAD" > "4. Launch the installer"

02-02 Installing IJCAD

1. Decompress the installer (unzip)

Right-click the downloaded IJCAD installer and click [すべて展開].


The installer is a compressed file. Please be sure to decompress it.




2. Select decompression destination

The 「展開先の選択とファイルの展開」 dialog is displayed.

There is no need to change the deployment destination. Just click the [展開] button.




Once the decompression is complete, a folder will be created based on the installer name.



3. Execute [setup.exe]


Open the decompress file and right click [setup.exe]. Find and click [管理者として実行].



「ユーザーアカウント制御」 dialog may appear. Click 「はい」 to start the installer.

4. Launch the installer


When the installer starts, click [Next].



5. Confirm the license agreement

Please read the IJCAD Software License Agreement, Maintenance Service Terms, and Support Policy (links).


If you agree, check the two checkboxes and click [Next].



6. Select installation destination


Just click the [Next] button.

You can also select the installation destination folder from [...].




7. Installation

Installation will begin.



8. Installation completed

Click [Finish] to exit, and click [Launch] to start IJCAD.



Once the installation is complete, an IJCAD icon will be added to the desktop or start menu.



03 USB update

- ※ If you have ordered a paid update service when purchasing the USB, please skip this chapter and proceed to "04 Starting IJCAD".
- ※ When updating for the first time, you will be required to enter the serial key. The serial key will be sent in [PDF] via email with the title "【IJCAD】ご注文の商品をお届けします(システムメトリックス)" or "【IJCAD】ご注文有難うございました(システムメトリックス)". Therefore, please prepare before updating.

03-01 Downloading USB Updater

1. Access download page

You can download the USB Updater from the web page below.

<https://manage.ijcad.jp/trials/downloads/no-auth>

Click[ダウンロード] to download the product USB Updater installer.

The screenshot shows a grid of software download options. At the top, there are three yellow 'ダウンロード' (Download) buttons. Below them are three software cards: 'IJCAD: Arch [64bit]', 'IJCAD: Arch+ [64bit]', and 'IJCAD: Civil [64bit]'. Each card has a 'ダウンロード' button. A light blue box contains Japanese text: '各プログラムの個別インストールが必要な場合、こちらからダウンロードしてください。スタンドアロン版、USB版から移行される方は【IJCAD 移行プログラム】をご利用ください。なお、移行前に必ずこちらの記事をご一読ください。' Below this are three more software cards: 'B-rite Runtime', 'IJCAD 移行プログラム', and 'USB Updater'. The 'USB Updater' card has a red box around its 'ダウンロード' button.

2. Decompress the installer (unzip)

Right-click the downloaded IJCAD installer and click [すべて展開].

The installer is a compressed file. Please be sure to decompress it.

IJCAD のインストール同様、展開先を選択し展開してください。

3. Start USB Updater


Open the folder created by unzipping and double-click [usbUpdater.exe] in the folder to start USB Updater.

03-02 Updating an empty USB

※ Please do not unplug the USB until you click "OK" in Step 4.


1. Starting USB Updater

Insert the USB and launch USB Updater.



2. Enter serial key


Enter the serial key in the serial key input field of [期間更新] and click [入力シリアルを使用].



3. Check the precautions


A caution dialog will be displayed.

If there is no problem with the contents, check 「同意する」 (I agree) and click the [OK] button.



4. Completion of update work

When the update completion message is displayed, click [OK].




This completes the USB update process.

03-03 Update configured USB

※ Please do not unplug the USB until you click "OK" in Step 4.


1. Starting USB Updater

Insert the USB and launch USB Updater.



2. USB update


Click the button [現在のシリアルを更新].



3. Check the precautions


A caution dialog will be displayed.

If there is no problem with the contents, check 「同意する」 and click the [OK] button.



4. Completion of update work

When the update completion message is displayed, click [OK].



This completes the USB update process.

04

Starting IJCAD

04-01 Starting IJCAD for the first time

1. Insert USB key

Insert the IJCAD USB key into the USB drive of your computer.

* If the USB is successfully loaded, the back of the USB will turn red.

2. Starting IJCAD for the first time

Double-click the IJCAD icon on the desktop to start IJCAD.



While the software is primarily intended to be used by the same user who installed it, please refer to the following article if you must use it with a different account.


[インストールユーザーと異なるユーザーで利用する場合の注意点](#)

3. Set file associations

When you start it for the first time, the following setting screen for association with DWG will be displayed. Select as required.

If you select 「Always reassociate DWG files with IJCAD(Recommended)」in the first line, DWG will always be associated with IJCAD.

From now on, double-clicking the DWG file will open IJCAD.



4. Start IJCAD

IJCAD startup has completed.

05

Update Installation

When you want to update version of the installed product, update installation is necessary.

※Update installation is not required when installing IJCAD 2024 SP0.

Update installation differs from version up and means to update within the same fiscal year version.

Example:

Update installation: IJCAD 2026 SP0 → IJCAD 2026 SP1

Version up: IJCAD 2025 SP1 → IJCAD 2026 SP0

05-01 Before Update Installation

Although the information of CUI and template customization could be inherited without transit operation, first take your backup before update installation for your safety.

- Cuix file, etc.
⇒C:¥Users¥(User Name)¥AppData¥Roaming¥IntelliJapan
¥IJCAD(Grade)¥R26¥en-US¥Support
- Template File
⇒C:¥Users¥(User Name)¥AppData¥Local¥IntelliJapan
¥IJCAD(Grade)¥R26¥en-US¥Template


05-02 Update Installation procedure

1. Download the latest Installer

The latest version can be downloaded from the WEB page
(<https://manage.ijcad.jp/trials/downloads>)

2. Launch the Installer


Please Unzip the downloaded folder, right-click on [setup.exe] in the folder, and run it as an administrator. The installer will start.



3. Update Installation

After launching the installer, a dialog like the right picture appears.

Click [はい] button



4. Installation

The installation will begin, so please wait until it is complete.

The update installation is now complete.

*If the update installation does not go well, please uninstall IJCAD once and then perform a new installation.

06

Uninstalling IJCAD

06-01 Uninstalling IJCAD


Uninstallation is possible in two ways from [アプリと機能] and from [コントロールパネル].

◆ Uninstall procedure from [アプリと機能]


- Go to the uninstallation screen
Right-click the Windows Start menu,
click [Settings] > [Apps] > [Installed Apps]
then follow the steps below to open the uninstall menu.



- Uninstall
The installer will start, and a confirmation message will be displayed, so click the [はい] button.



- Completion of uninstallation
When the completion dialog appears, click the [Finish] button.



4. Delete user data

After uninstalling, please delete your user data.

C:\Users\[username]\AppData\Roaming\IntelliJapan
 \IJCAD [product name or grade] \R25

◆ Uninstall procedure from [コントロールパネル]


1. Go to the uninstallation screen

Open Control Panel and select [プログラムのアンインストール].




2. Uninstall

Select the IJCAD you want to uninstall from the list, right-click the mouse, and click [アンインストール] from the menu.



The installer will start, and a confirmation message will be displayed, so click the [はい] button.



3. Completion of uninstallation

When the completion dialog appears, click the [Finish] button.



4. Delete user data

After uninstalling, please delete your user data.

C:\Users\ [username] \AppData\Roaming\IntelliJapan
 \IJCAD [product name or grade] \R26